

DynaPDF 3.0

Implementation Notes

----- Changed data types -----

The following data types contain extensions due to new features or values which were not supported in DynaPDF 2.x. Only new constants or members are listed. Almost all changes are backward compatible.

```
typedef enum
{
    ...
    atRichMediaExec // PDF 1.7 Extension Level 3
} TActionType;

typedef enum
{
    aiUserDefined // Internal, used to store undefined values in
                  // imported annotations
} TAnnotIcon;

typedef enum
{
    ...
    atMovieAnnot, // PDF 1.2
    atPrinterMark, // PDF 1.4
    atProjection, // PDF 1.7 Extension Level 3
    atRichMedia, // PDF 1.7 Extension Level 3
    atScreen, // PDF 1.5
    atTrapNet // PDF 1.3
} TAnnotType;

typedef enum
{
    ...
    bsUserDefined // Internal, used to store undefined values in
                  // imported annotations
} TBorderStyle;

typedef enum
{
    ...
    civCustom // PDF 1.7 Extension Level 3, the collection view is
              // presented by a SWF file.
} TColView;
```

```

typedef enum
{
    ...
    diPDFX_Conf      = 9,   // GetInDocInfo() or GetInDocInfoEx() only. The
                           // value of the GTS_PDFXConformance key.
    diCreationDate  = 10,  // GetInDocInfo() or GetInDocInfoEx() or after
                           // ImportPDFFile() was called.
    diModDate        = 11  // GetInDocInfo() or GetInDocInfoEx() only
} TDocumentInfo;

// This callback function is used by EnumHostFontsEx(). Because DynaPDF
// supports now Unicode and Ansi font file paths the returned file path
// can be in Unicode or Ansi format.
typedef SI32 PDF_CALL TEnumFontProcEx(
    const void* Data,
    const UI16* FamilyName,
    const char* PostScriptName,
    SI32 Style,
    TFontBaseType BaseType,
    TEnumFontProcFlags Flags, // Renamed, see below (LBOOL Embeddable)
                           // previously
    const char* FilePath);

typedef enum
{
    efpAnsiPath     = 0, // Code page 1252 on Windows, UTF-8 otherwise
    efpUnicodePath  = 1, // FilePath is in Unicode format.
    efpEmbeddable   = 2 // The font has embedding rights.
} TEnumFontProcFlags;

typedef enum
{
    ...
    faiUserDefined // Internal, used to store undefined values in
                   // imported annotations
} TFileAttachIcon;

typedef UI32 TImportFlags2;
#define if2UseProxy 4 // Not meaningful for PDF files which are
                  // loaded from a memory buffer. If set, all
                  // streams are loaded from the file on demand
                  // but they are never hold in memory. This
                  // reduces drastically the memory usage and
                  // enables the processing of almost arbitrary
                  // large PDF files with minimal memory usage.
                  // The corresponding PDF file must not be
                  // deleted before CloseFile() or CloseFileEx()
                  // was called.

// The parameter Recursive of the function SetCMapDir uses now this
// enum instead of a Boolean value.
typedef enum
{

```

```

    lcmDefault    = 0, // Load the Cmaps in the directory now
    lcmRecursive  = 1, // Load sub directories recursively
    lcmDelayed    = 2 // Load the Cmap files only if required
} TLoadCMapFlags;

typedef enum
{
    ...
    naUserDefined // Non predefined action
} TNamedAction;

typedef enum
{
    ...
    ovNotSet // Internal
} TOCVisibility;

typedef enum
{
    ...
    taNotSet = 4 // Internal -> Do not use this value!
} TTextAlign;

typedef enum
{
    ...
    toAnnots = 4, // Annotation order -> PDF 1.7 Extension Level 3
    toFields = 5 // Widget order      -> PDF 1.7 Extension Level 3
} TTabOrder;

struct TPDFAnnotationEx
{
    ...
    UI32 PageIndex;    // The page index is used to sort form fields.
                       // See SortFieldsByIndex().
    LBOOL MarkupAnnot; // If true, the annotation is a markup
                       // annotation. Markup annotations can be
                       // flattened separately, see FlattenAnnots().
    float Opacity;    // Opacity < 1.0 = Transparent
                       // Markup annotations only
    /* 24 Reserved fields follow */
};

struct TPDFExtGState
{
    ...
    LBOOL SoftMaskNone; // Disables the active soft mask
    void* SoftMask;   // Soft mask pointer or NULL. See
                       // CreateSoftMask() for further information.

    /* 7 reserved fields follow */
};

```

```

struct TPDFFieldEx
{
    ...
    UI32          PageIndex;      // Array index to change the tab
                                // order, see SortFieldsByIndex().
    const void*   IBarcode;       // If present, this field is a
                                // barcode field. The field type is
                                // set to ftText since barcode fields
                                // are extended text fields. See
                                // GetBarcodeDict().
    const void*   ISignature;     // Signature fields only. Present
                                // only for imported signature fields
                                // which have a value. That means the
                                // file was digitally signed. See
                                // GetSigDict().
                                // Signed signature fields are always
                                // marked as deleted!
};

// This structure has been changed since the old functions
// GetInNamedDest() and GetInNamedDestCount() are no longer supported.
// GetInNamedDestCount() returns always zero. See description at the
// function section.
struct TPDFNamedDest
{
    UI32          StructSize;    // Must be initialized to
                                // sizeof(TPDFNamedDest)
    const char*   NameA;
    const UI16*   NameW;
    UI32          NameLen;
    const char*   DestFileA;
    const UI16*   DestFileW;
    UI32          DestFileLen;
    SI32          DestPage;
    struct TPDFRect DestPos;
    TDestType      DestType;
};

struct TPDFParseInterface
{
    ...
    TBEGINLayer* BeginLayer; // Starts the definition of a layer
    TENDLayer*   EndLayer;   // Finishes the layer. Consider the new
                            // visibility state!
/* 25 reserved fields follow */
};

----- Changed functions -----

```

GetInNamedDestCount(), GetInNamedDest():

GetInNamedDestCount() returns always zero, also if the file contains named destinations. These functions were provided for a few customers who depend on named destinations. Because

DynaPDF 2.x resolved all named destinations during import there was no other way to access them.

This behavior has been changed in DynaPDF 3.0. Named destinations are now imported like any other object. The new functions to access named destinations are GetNamedDest() and GetNamedDestCount(). The destinations are available after the file was imported. The old functions are no longer included in any DynaPDF interface (with exception of the abstract C++ interface), although the functions do still exist in the DLL.

Sorry, but the required overhead to get these functions working in DynaPDF 3.0 is simply too large...

SetCMapDir()

The parameter Recursive has been renamed to Flags and the data type was changed from LBOOL (long Boolean) to the enum TLoadCMapFlags. This change was required because it must be possible to load external CMaps delayed to improve the loading time. The change is backward compatible but the function parameter must be changed when recompiling the application.

SetUseSwapFile() , SetUseSwapFileEx() :

The contents of pages, templates, and patterns are no longer written to the temp file also if SwapContents is set to true. Only images are written to the temp file. In DynaPDF 3.0 it is possible to flush finish pages to the output file whenever necessary, see FlushPages() in the help file.

----- Other changes -----

EditPage() :

When opening an existing page for editing DynaPDF does now the following:

- When the page is opened the first time, DynaPDF parses the content stream to determine the graphics state at the end of the stream. Errors in the content stream will be repaired if possible.
 - If the content stream contains non-repairable errors then editing is still possible but the result is of course undefined. Errors are written to the error log.
 - When closing the page, the graphics state is stored in a compact format so that it is not required to parse the page again when it will be edited again. Prior versions simply enclosed the content stream into save/restore graphics state operators if the content stream did not start with a save graphics state operator. Although this produced correct results in most cases, there could be problems with malformed content streams which end with unbalanced restore graphic state operators.

OpenImportFile() , OpenImportBuffer()

When opening a PDF file the function reads the cross-reference tables and tries to load the required top level objects such as the Trailers, Catalog, Page Tree, and Encryption dictionaries.

If the file contains damages that prevents loading of these objects then the function falls back into repair mode and tries to repair the file. The function rebuilds then the cross-reference table by scanning all the objects in the file. Errors and warnings are written to the new error log. If the

file could be successfully repaired then the function returns success and no error will be raised via the normal exception handling.

It is not always possible to identify damages when opening a PDF file, e.g. if it contains only partial damages which affect specific pages only. If it is not possible to load certain pages due to errors then it is possible to load the file explicitly in repair mode. This makes of course only sense if the file was not already loaded in repair mode. Whether this is the case can be checked with the function GetInRepairMode(). Take a look at the description of OpenImportFile() in the help file for further information.

OpenImportBuffer() supports now an additional flag to avoid copying of the input buffer. The usage of this flag is allowed in programming languages which support pointers, such as C/C++, Delphi, and probably also Visual Basic. .Net language can use this flag only if the buffer was allocated with AllocHGlobal() because the pointer of a managed memory block can change every time when another function is executed.

See OpenImportBuffer() for further information.

Internal color format:

The internal color format in the graphics state was changed from 8 bits to 16 bits per channel.

Transparent images:

Images with an alpha channel are now always inserted transparent. The alpha channel is converted to a soft mask to preserve the transparency.

----- New Functions -----

```
// Rendering API
rasAbort()
rasAttachImageBuffer()
rasCreateRasterizer()
rasDeleteRasterizer()
rasCreateRasterizerEx()
rasResizeBitmap()

// Page Cache
rasChangeBackColor()
rasCloseFile()
rasCreatePageCache()
rasDeletePageCache()
rasExecBookmark()
rasGetCurrPage()
rasGetCurrZoom()
rasGetDefPageLayout()
rasGetPageAt()
rasGetPageLayout()
rasGetPageScale()
rasGetRotate()
rasGetScrollPos()
rasGetScrollRange()
rasInitBaseObjects()
rasInitColorManagement()
```

```
rasInitialize()
rasMouseDown()
rasMouseMove()
rasPaint()
rasProcessErrors()
rasResetMousePos()
rasResize()
rasScroll()
rasSetCMapDirA()
rasSetCMapDirW()
rasSetDefPageLayout()
rasSetPageLayout()
rasSetPageScale()
rasSetRotate()
rasSetThreadPriority()
rasZoom()
```

```
// DynaPDF API
pdfAddRasImage()
pdfBeginTransparencyGroup    // PDF 1.4
pdfClearErrorLog()
pdfCreateBarcodeField()
pdfCreateGoToRActionW()      // PDF 1.7, supports an Unicode path
pdfCreateGoToRActionExUA()   // PDF 1.7, supports an Unicode path
pdfCreateGoToRActionExUW()   // PDF 1.7, supports an Unicode path
pdfCreateLaunchActionExA()
pdfCreateLaunchActionExW()    // PDF 1.7
pdfCreateSoftMask()          // PDF 1.4
pdfFlushPages()
pdfGetBarcodeDict()
pdfGetDocUsesTransparency()
pdfGetErrLogMessage()
pdfGetErrLogMessageCount()
pdfGetInFieldCount()
pdfGetInRepairMode()
pdfGetIsTaggingEnabled()     // See OpenTag() in the help file
pdfGetNamedDest()
pdfGetNamedDestCount()
pdfGetPageBBox()
pdfGetPageObject()
pdfGetPageOrientation()
pdfGetSigDict()
pdfHaveOpenPage()
pdfInsertImageExA()          // These functions are not new. Only the
pdfInsertImageExW()          // Unicode version was added.
pdfRenderPage()
pdfRenderPDFFileA()
pdfRenderPDFFileW()
pdfSetExtFillColorSpace()
pdfSetExtStrokeColorSpace()
pdfSetFillColorF()           // Accepts an array or float
pdfSetFontSearchOrderEx()
pdfSetMaxErrLogMsgCount()
pdfSetStrokeColorF()         // Accepts an array or float
```